MOMAP User Guide Version 2022A



Version 2022A

April, 2022

MOMAP User Guide

Version 1.0 edited by:

Dr. Yingli Niu, Dr. Linjun Wang, Dr. Wenqiang Li, Mr. Shuo Zhang, Dr. Hua Geng, Dr. Qian Peng, and

Dr. Jianming Chen

Version 2019B edited by:

Dr. Qikai Li, Dr. Yingli Niu, Dr. Linjun Wang, Dr. Qian Peng, and Ms. Lihui Yan

Versions 2020A, 2020B, 2021A, 2021B, 2022A edited by:

Dr. Qikai Li

Released by Hongzhiwei Technology (Shanghai) Co., Ltd and Z.G. Shuai Group The information in this document applies to MOMAP 2022A

Preface

This MOMAP User Guide is composed of two parts, that is, the part on photophysical properties and the part on transport properties, which reflects the functionalities of current MOMAP version 2022A.

The photophysical property part introduces the quantum chemistry calculations, vibrational analysis with electron-vibration coupling (EVC), and calculations on absorption spectrum, emission spectrum, radiative rate, internal conversion, intersystem crossing *etc*. by examples of the fluorescence spectrum and phosphorescence spectrum calculations. In addition, the Guide also touches upon the sum-over-states approach and Herzberg-Teller effect in calculations.

The transport property part introduces the procedure of charge carrier transport calculations by using naphthalene molecule as an example, with detailed descriptions on calculations of transfer integral, reorganization energy, random walk *etc*. In the meantime, the Guide also gives descriptions on data analysis *etc*. which facilitates the users to incorporate the calculations into their research work.

Many people are engaged in the compilation of this Guide, the main participants are: Prof. Qikai Li from Tsinghua University, Dr Yinli Niu from Beijing Jiaotong University, Prof. Linjin Wang from Zhejiang University, Prof Qian Peng from Institute of Chemistry, Chinese Academy of Sciences, Ms Lihui Yan from Hongzhiwei Technology (Shanghai) Co. Ltd., Ms Lu Wang from Tsinghua University, and more.

Qikai Li Department of Chemistry Tsinghua University April 27, 2022

Contents

1. Introduction to MOMAP
1.1 Overview
1.2 On photophysical properties2
1.3 How to cite MOMAP4
2. MOMAP installation
2.1 Download MOMAP5
2.2 Install MOMAP
3. Duschinsky Rotation Matrix and Vibrational Analysis7
3.1 Overview7
3.2 Start a calculation
3.3 Program outputs
4. Fluorescence Spectrum Calculation
4.1 Overview
4.2 Start a calculation
4.3 Modifying control file9
4.4 Verify convergence of correlation function and obtain results10
5. Internal Conversion (IC) Rate Constant
5.1 Overview
5.2 Calculate non-adiabatic coupling matrix element (NACME)11
5.3 Start a calculation11
5.4 Modify control file12
5.5 Verify convergence of correlation function and obtain results
6. Phosphorescence Spectrum Calculation
6.1 Overview
6.2 Start a calculation
6.3 Modify control file13
6.4 Verify convergence of correlation function and obtain results14
6.5 Intersystem crossing14
7. Obtain Information from QC packages15

7.1 Optimization calculation on ground state (S ₀)	15
7.2 Frequency calculation at the optimized S_0 geometry	15
7.3 Transition dipole moment (absorption) at the optimized S ₀ geometry	16
7.4 Optimization calculation on lowest singlet excited state (S ₁)	16
7.5 Frequency calculation at the optimized S ₁ geometry	17
7.6 Transition dipole moment (emission) at the optimized S1 geometry	17
7.7 Adiabatic energy difference between S_0 and S_1 states	
7.8 Transition electric field and NACME at the optimized S ₁ geometry	
8. Transport: Background	20
8.1 Charge Transfer Rate	20
8.2 Pauli Master Equation	20
8.3 Monte Carlo Simulation	21
8.4 Lattice Random Walk	21
8.5 Charge Carrier Mobility	23
9. Transport: Quick Start	25
9.1 Naming conversions	25
9.2 Create a new calculation	25
10. Transport: Looking into the details	
10.1 Transport preparation	
10.2 Transfer Integral Calculations	40
10.3 Reorganization Energy Calculations	41
10.4 Collect Transfer Integrals	42
10.5 Analyze Reorganization Energies	43
10.6 Monte Carlo (MC) simulations	43
10.7 Calculate Random Walk Mobilities	44
10.8 Gather data	48
11. Transport: Parameters	50
11.1 Transport environment variables	50
11.2 Transport input variables	51
12. PYSOC input variables	55
13. MOMAP Tools	56
13.1 MOMAP tool for preparing Gaussian oniom input files	

Part one: Photophysical Properties

1. Introduction to MOMAP

1.1 Overview

MOMAP (Molecular Materials Property Prediction Package) is a suite of programs for predicting the properties of polyatomic molecules, which is jointly developed by the Key Laboratory of Organic Solids (Institute of Chemistry Chinese Academy of Sciences) and Prof. Zhigang Shuai's research group (Department of Chemistry, Tsinghua University).

MOMAP allows users to study the photophysical properties and charge transport properties of a given molecule. The first version of this user guide focuses on introducing theoretical calculations on photophysical properties, however, this new version will also include calculations on charge transport properties.

1.2 On photophysical properties

The excitation, radiative decay and non-radiative decay are the basic photophysical and photochemical processes. They all have direct impact on the optical and electrical properties of a molecule.

The key photophysical processes, which can be described by Jablonski energy diagram, as shown in Fig. 1. MOMAP can simulate the spectrum of a given molecule, including the absorption, fluorescence and phosphorescence spectrum. In addition, MOMAP is also able to calculate transition rate constants between two electronic states as well, including the radiative and non-radiative decay rate constants for the internal conversion (IC) process and intersystem crossing (ISC) process.



Fig. 1 Jablonski energy diagram

As we know, the photophysical properties are tightly related to the various properties of ground and excited states, which are the basis to carry out calculations in MOMAP. The various module dependencies on common quantum chemistry (QC) calculations are shown in Fig. 2.



Fig. 2 Dependencies and relationships between MOMAP and QC calculations

In order to perform the calculation, including geometries, single point energy and vibrational modes of ground and excited states, as well as transition dipole moment, non-adiabatic coupling and spin-orbit coupling constant between ground and excited states, some key information should be provided to MOMAP. This information can be obtained from many other sophisticated quantum chemistry calculation packages, such as Gaussian, Q-Chem, TURBOMOLE, NWChem, ORCA, Dalton, ADF and BDF *etc.* The calculation details will be given in the following chapters.

1.3 How to cite MOMAP

Users who publish papers based on MOMAP calculations are required to cite: MOMAP – Molecular Material Property Prediction Package. http://www.momap.net.cn

Optionally, you may cite the following literatures:

- 1) Peng, Q.; Yi, Y.; Shuai, Z.; Shao, J., *The Journal of Chemical Physics*, 2007, 126, 114302.
- 2) Peng, Q.; Yi, Y.; Shuai, Z.; Shao, J., Journal of the American Chemical Society, 2007, 129, 9333-9339.
- 3) Niu, Y.; Peng, Q.; Shuai, Z., Science in China Series B: Chemistry, 2008, 51, 1153-1158.
- 4) Niu, Y.; Peng, Q.; Deng, C.; Gao, X.; Shuai, Z., *The Journal of Physical Chemistry A*, **2010**, *114*, 7817-7831.
- 5) Peng, Q.; Niu, Y.; Shi, Q.; Gao, X.; Shuai, Z., *Journal of Chemical Theory and Computation*, **2013**, *9*, 1132-1143.
- 6) Shuai, Z., Chinese Journal of Chemistry, 2020, 38, 1223-1232.

2. MOMAP installation

2.1 Download MOMAP

MOMAP can be downloaded from the following site: <u>http://www.momap.net.cn/index.php/download</u>

2.2 Install MOMAP

(1) Operating System

MOMAP is mainly targeted to be running in a UNIX-like environment. However, it can also be installed on Windows and MacOS.

(2) Install MOMAP package

The MOMAP package for Linux is downloaded as a single zipped installable run file, e.g., momap-2022A-linux-el7-mpich2.run.gz

Unzip the file and add executable attribute to the file, and install MOMAP package by running:

```
$ gunzip momap-2022A-linux-el7-mpich2.run.gz
```

```
$ chmod a+x momap-2022A-linux-el7-mpich2.run
```

```
$ ./momap-2022A-linux-el7-mpich2.run
```

Or more generally, install MOMAP package by running:

```
$ sh momap-2022A-linux-el7-mpich2.run
```

If MOMAP is to be run under the Ubuntu Linux system, before we start to install MOMAP, we need to promote the user rights and make the user to be an administrator. Here, we will show you how to make a user an administrator in Ubuntu through the command line:

```
$ sudo usermod -aG sudo sampleuser
```

You can verify that the user is now in the "sudo" group by checking the groups a user belongs to, through the following command:

\$ groups sampleuser

Log out and log back in again for it to take effect, then we can proceed to have a normal MOMAP installation.

Before using the MOMAP, one should first set up the running environment, add the following line to ~/.bashrc if Bash is used:

. installed momap folder/env.sh

Log out and log back in again for it to take effect, then we can proceed to run MOMAP.

If Bash shell is used, one can add the following line:

export MOMAP LICENSE DEBUG=TRUE

in file ~/.bashrc to activate output of license debug information.

In some supercomputing centers, the SSH port may not be the default 22, in that case, we need to setup the SSH environment variable, for example:

export MOMAP SSH PORT=5577

As to the specific port used, please contact the supercomputing center's system administrator for information.

If the Environment Modules is installed, one can use the command module to manage the MOMAP running environment, please refer to the installation guide for more details.

For more information, please refer to the **MOMAP Installation Guide**.

3. Duschinsky Rotation Matrix and Vibrational Analysis

3.1 Overview

MOMAP is able to analyze Duschinsky rotation and normal mode vibrations, which is based on evc int and evc cart subprograms¹.

In the following part of this guide, this kind of calculation will be termed as evc calculation.

The evc calculation can use outputs from other QC programs, such as Gaussian, Q-Chem, TURBOMOLE, ChemShell, Dalton, MOLPRO, DFTB and MOPAC *etc*. It can also read data from the output files, including vibrational frequencies and force constant matrix, and calculate normal mode displacement, Huang-Rhys factor, reorganization energy and Duschinsky rotation matrix between initial and final electronic states under both internal coordinate and Cartesian coordinate.

3.2 Start a calculation

The evc calculation requires the basic information on initial and final electronic states. Thus, to begin an evc calculation, you need to designate the related file names in the MOMAP input file (i.e., momap.inp).

Here is an example of the simplest evc input file. For the Gaussian output files, you have to provide the corresponding .fchk files as well.

Take tests/azulene/evc as an example, edit momap.inp, and add the following in the file:

When the evc input file is ready, users can do the calculation by running:

```
$ momap.py -i momap.inp -n 4
```

The example also contains a run script file, users may modify the file, for example, by changing

¹ dushin_int and dushin_cart programs are modified from dushin program, which is written by Prof. Jeffrey R. Reimers (J. Chem. Phys. vol. 115, 9103-9109, 2001)

the np option from 4 to 8, and perform calculation by running the script file:

\$./run

Except for ffreq(1) and ffreq(2) parameters, evc program also allows user to project reorganization energy onto the internal coordinate, to take account of isotope effect, and to configure many other advanced settings *etc*. Please refer to Appendix for more parameter settings.

3.3 Program outputs

The main results obtained from this calculation are the properties between initial and final electronic states - normal mode displacement, Huang-Rhys factor, reorganization energy and Duschinsky rotation matrix. The information is kept in evc.cart.dat and evc.dint.dat.

(1) evc.cart.dat

Use Cartesian coordinate to calculate the above properties.

(2) evc.dint.dat

Use internal coordinate to calculate normal mode displacement, Huang-Rhys factor and reorganization energy, while using cartesian coordinate to calculate Duschinsky rotation matrix.

Please check the reorganization energy results between evc.cart.dat and evc.dint.dat. If the energy difference is small (< 1000 cm⁻¹), then use the results in evc.cart.dat to do the next calculations. However, if the energy difference is large, then use evc.dint.dat to do the next calculations.

4. Fluorescence Spectrum Calculation

4.1 Overview

MOMAP is able to simulate fluorescence spectrum and calculate the corresponding radiative decay rate constant based on the TVCORF_SPEC² and TVSPEC_SPEC subprograms. The TVCORF_SPEC subprogram is used to calculate the thermal vibration correlation function (TVCF), while the TVSPEC_SPEC subprogram is used to simulate the fluorescence spectrum.

In the following part of this guide, this kind of calculation will be termed as rad_FL calculation.

4.2 Start a calculation

To start a rad_FL calculation, you need a *.dat file, an MOMAP control file, and an optional parallel control file. The *.dat file is obtained from the previous mentioned evc calculation. A MOMAP control file is used to control how TVCORF_SPEC and TVSPEC_SPEC subprograms behavior. An optional parallel control file is used to control how many computing processes will be used.

An example for performing rad_FL calculation with azulene is put in directory tests/azulene/kr. The files needed for this calculation are as follows:

(1) evc.cart.dat

Evc calculation result file.

(2) momap.inp

MOMAP control file.

(3) nodefile (optional, it may be automatically generated by running options -n #)
 Parallel machinefile to control how many computing processes will be used.

4.3 Modifying control file

Here is an example of the MOMAP control file for a rad_FL calculation, it shows the various parameters and their meanings. Users may need to change the parameters accordingly before performing a rad_FL calculation.

² TVCORF_SPEC_para subprogram is available for parallel computation.

```
[kr]$ cat momap.inp
do spec tvcf ft
                         = 1
                                                        # toggle correlation function calculation, 1 or 0
do_spec_tvcf_spec
                                                        # toggle fluorescence spectrum calculation, 1 or 0
                         = 1
&spec_tvcf
  DUSHIN
                                                        # toggle Duschinsky rotation effect, .t. or .f.
                    = .t.
                    = 300 K
                                                        # temperature
  Temp
  tmax
                    = 5000 \text{ fs}
                                                        # integration time, at least 5000 fs
                    = 0.001 \text{ fs}
                                                        # integration timestep, maximum not exceeding 0.001 fs
  dt
                    = 0.075092 au
                                                        # adiabatic excitation energy
  Ead
                    = 0.92694 debye
                                                        # electronic dipole moment of absorption (GS)
  EDMA
                    = 0.64751 debye
  EDME
                                                        # electronic dipole moment of emission (ES)
  FreqScale
                    = 1.0
                                                        # frequency scaling factor
                    = "evc.cart.dat"
  DSFile
                                                        # input dushin file
                    = 0.3 au
  Emax
                                                        # upper bound of spectrum frequency
                    = 0.00001 au
                                                        # output energy interval
  dE
                    = "spec.tvcf.log"
                                                        # output file for logging
  logFile
  FtFile
                    = "spec.tvcf.ft.dat"
                                                        # output file for correlation function info
  FoFile
                    = "spec.tvcf.fo.dat"
                                                        # output file for spectrum function info
  FoSFile
                    = "spec.tvcf.spec.dat"
                                                        # output file for spectrum info
```

If the users want to use the *sum-over-states* approach to calculate the spectrum at absolute zero (0 K), please refer to directory examples/azulene/sumstat for more details.

4.4 Verify convergence of correlation function and obtain results

Correlation function must be converged before obtaining any calculation results. To verify, plot a graph using the first 2 columns in the spec.tvcf.ft.dat, which are time and real part of the correlation function (TVCF_RE). The TVCF_RE should be very close to zero and stop oscillating before it reaches the integration time limit. Fig. 3 shows a plot of a converged correlation function.

The radiative decay rate constant can be found at the end of spec.tvcf.log file, while the fluorescence spectrum information can be obtained from spec.tvcf.spec.dat.



Fig. 3 Distribution of time vs real part of a converged correlation function

5. Internal Conversion (IC) Rate Constant

5.1 Overview

MOMAP is also able to calculate internal conversion (IC) rate constant based on the TVCORF_IC³ and TVSPEC_IC subprograms. The TVCORF_IC subprogram is used to calculate thermal vibration correlation function (TVCF), while the TVSPEC_IC subprogram is used to determine the relationship between IC rate constant and energy gap.

In the following part of this guide, this kind of calculation will be termed as nonrad calculation.

5.2 Calculate non-adiabatic coupling matrix element (NACME)

Unlike the rad_FL calculation, The NACME should be obtained before performing a nonrad calculation.

In MOMAP, the get-nacme function is used to read the transition electric field and vibration information from Gaussian output and calculate electronic coupling term. This process is integrated into evc_int and evc_cart subprogram. Users need to provide the Gaussian electric field calculation result and toggle on the NACME calculation in MOMAP control file momap.inp. The other steps are the same as for a normal evc calculation. After finishing the calculation, a *.nac file will be generated, and it is used in the nonrad calculation.

5.3 Start a calculation

To start a nonrad calculation, you need a *.dat file, a *.nac file, a MOMAP control file, and an optional parallel control file. The *.dat file is the evc result file. The *.nac is the NACME calculation result file. As for all MOMAP calculations, a MOMAP control file is needed for TVCORF_IC and TVSPEC_IC subprograms. A parallel control file is used to control how many computing processes will be used.

An example for performing nonrad calculation with azulene are put in directory tests/azulene/kic/kic. The files needed in this example are as follows:

(1) evc.cart.dat

Evc calculation result file.

³ TVCORF_IC_para subprogram is available for parallel computation.

(2) evc.cart.nac

NACME result file.

(3) momap.inp

MOMAP control file.

(4) nodefile (optional, it may be automatically generated by running options -n #)Parallel machinefile to control how many computing processes will be used.

5.4 Modify control file

Here is an example of the MOMAP control file for a nonrad calculation, it shows the various parameters and their meanings. Users may need to change the parameters accordingly before performing a nonrad calculation.

[kic/kic]\$ <mark>cat</mark>	momap.inp	
do_ic_tvcf_ft	= 1	# toggle internal conversion correlation function, 1 or 0
do_ic_tvcf_spec	c = 1	# toggle internal conversion spectrum, 1 or 0
tia twof		
AIC_UVUI		" to a la Derall's also actedian affrat to an f
DUSHIN	= .t.	# toggle Duschinsky rotation effect, .t. or .f.
Temp	= 300 K	# temperature
tmax	= 5000 fs	# integral interval of correlation function, at least 5000 fs
dt	= 0.001 fs	# integration timestep of correlation function, no more than 0.001 fs
Ead	= 0.075092 au	# adiabatic excitation energy difference between two states
DSFile	= "evc.cart.dat"	# input dushin file
CoulFile	= "evc.cart.nac"	# input nacme info file
Emax	= 0.3 au	# upper bound of spectrum frequency
logFile	= "ic.tvcf.log"	# output file for logging
FtFile	= "ic.tvcf.ft.dat"	# output file for correlation function info
FoFile	= "ic.tvcf.fo.dat"	# output file for spectrum function info
/		

5.5 Verify convergence of correlation function and obtain results

Make sure the correlation function is converged, this is very important. The verification process can be found in section 4.4.

The internal conversion (IC) rate constant can be found at the end of ic.tvcf.log file. The relationship between IC rate constant and energy gap can also be obtained from the ic.tvcf.log file.

6. Phosphorescence Spectrum Calculation

6.1 Overview

MOMAP is also able to simulate the phosphorescence spectrum and calculate the corresponding radiative rate constant and intersystem crossing (ISC) rate constant based on the TVCORF_SPEC⁴ and TVSPEC_SPEC subprograms. The TVCORF_SPEC subprogram is used to calculate thermal vibration correlation function (TVCF), while the TVSPEC_SPEC subprogram is used to simulate phosphorescence spectrum.

In the following part of this guide, this kind of calculation will be termed as rad PL calculation.

6.2 Start a calculation

To start a rad_PL calculation, you need a *.dat file, a MOMAP control file and an optional parallel control file. The *.dat file is obtained from the previous evc calculation. The MOMAP control file is used to control the calculations of TVCORF_SPEC and TVSPEC_SPEC subprograms. The parallel control file is used to control now many computing processes will be used.

An example for performing a rad_PL calculation on Ir(ppy)₃ are put under directory tests/Irppy3. The files needed for this calculation are as follows:

(1) evc.cart.dat

Evc calculation result file.

(2) momap.inp

MOMAP control file.

(3) nodefile (optional, it may be automatically generated by running options -n #)
 Parallel machinefile to control how many computing processes will be used.

6.3 Modify control file

Here is an example of the MOMAP control file for performing a rad_PL calculation, it shows the various parameters and their functions. Change the parameters accordingly before carrying out the calculation.

⁴ TVCORF_SPEC_para subprogram is available for parallel computation.

```
[kr]$ cat momap.inp
do spec tvcf ft = 1
                                                        # toggle correlation function calculation, 1 or 0
do_spec_tvcf_spec = 1
                                                        # toggle fluorescence spectrum calculation, 1 or 0
&spec tvcf
 DUSHIN
                  = .t.
                                                        # toggle Duschinsky rotation effect, .t. or .f.
                  = 298 K
 Temp
                                                        # temperature
                  = 5000 \text{ fs}
                                                        # integration time, at least 5000 fs
  tmax
                   = 0.001 fs
                                                       # integration timestep, no more than 0.001 fs
 dt
                   = 0.0941289 au
 Ead
                                                       # adiabatic excitation energy
 EDMA
                   = 1.0 debye
                                                       # electronic dipole moment of absorption (GS)
 EDME
                  = 0.306909 debye
                                                        # electronic dipole moment of emission (ES)
 DSFile
                  = "evc.cart.dat"
                                                        # input dushin file
                   = 0.3 au
 Emax
                                                        # upper bound of spectrum frequency
                   = 0.00001 au
 dE
                                                        # output energy interval
 logFile = "spec.tvcf.log"
FtFile = "spec.tvcf.ft.dat"
FoFile = "spec.tvcf.fo.dat"
                                                        # output file for logging
                                                        # output file for correlation function info
                                                        # output file for spectrum function info
  FoSFile
                   = "spec.tvcf.spec.dat"
                                                        # output file for spectrum info
```

6.4 Verify convergence of correlation function and obtain results

Make sure the correlation function is converged. The verification process can be found in section 4.4 of this guide.

The radiative decay rate constant can be found at the end of spec.tvcf.log.dat file. The phosphorescence spectrum information can be obtained from the spec.tvcf.spec.dat file.

6.5 Intersystem crossing

Here is an example of the MOMAP control file for performing an ISC calculation:

```
[kisc]$ cat momap.inp
                                                     # toggle isc correlation function calculation, 1 or 0
do_isc_tvcf_ft = 1
do_isc_tvcf_spec = 1
                                                     # toggle isc spectrum calculation, 1 or 0
&isc tvcf
 DUSHIN
                                                     # toggle Duschinsky rotation effect, .t. or .f.
                  = .t.
 Temp
                  = 298 K
                                                     # temperature
                  = 5000 \text{ fs}
                                                     # integration time, at least 5000 fs
  tmax
                  = 0.001 fs
                                                     # integration timestep, no more than 0.001 fs
 dt
 Ead
                  = 0.0941289 au
                                                     # adiabatic excitation energy
 Hso
                  = 116.877376 cm-1
                                                     # Spin-orbit coupling constant
                  = "evc.cart.dat"
 DSFile
                                                     # input dushin file
                  = 0.3 au
                                                     # upper bound of spectrum frequency
 Emax
                  = "isc.tvcf.log"
                                                     # output file for logging
  logFile
                 = "isc.tvcf.ft.dat"
                                                     # output file for correlation function info
  FtFile
                  = "isc.tvcf.fo.dat"
  FoFile
                                                     # output file for spectrum function info
```

Again, the intersystem crossing (ISC) rate constant can be found at the beginning of isc.tvcf.fo.dat file.

7. Obtain Information from QC packages

In the following part of this guide, we will show you how to obtain the useful calculation results from various QC packages. The 1,4-distyrylbenzene molecule (DSB for short) and Gaussian 09 package are used to demonstrate the process.



The Gaussian 09 is used to do optimization and frequency calculations on the ground state (S_0) and the lowest singlet excited state (S_1) , the transition dipole moment and the transition electric field between S_0 and S_1 states.

7.1 Optimization calculation on ground state (S₀)

Once the initial geometry is constructed, we have to find the optimized S_0 geometry. The route section is set as #p opt b3lyp/6-31g*, which indicates an optimization at B3LYP/6-31G* level.

When the calculation is completed, locate the **last line with "SCF Done"** in the output *.log file in order to find the single point energy at the optimized S₀ geometry. In this example, the last line with "SCF Done" is like the following:

```
SCF Done: E(RB3LYP) = -849.172438992 A.U.
```

The complete results can be found in directory tests/DSB/opt_and_frequency.

7.2 Frequency calculation at the optimized S₀ geometry

After finding the optimized S_0 geometry, we need to verify the optimization result and calculate its force constant matrix *via* frequency calculation. The route section is set as #p freq b3lyp/6-31g*, which runs a frequency calculation at the B3LYP/6-31G* level. You have to define the location of *.chk file in Link 0 Commands as well.

Use the Gaussian built-in command formchk to generate a *.fchk file based on the output *.chk. The *.fchk file contains readable force constant matrix information that is needed in dushin

calculation.

The complete results can be found in directory tests/DSB/opt_and_frequency.

In this example, the route section is set as #p opt freq b3lyp/6-31g*, which means we run optimization and frequency calculations at the same time. However, we recommend separating them into two types of calculation in order to avoid any possible mistakes.

7.3 Transition dipole moment (absorption) at the optimized S₀ geometry

After finding the optimized S_0 geometry, we can calculate transition dipole moment (absorption) and vertical excitation energy at this geometry. The route section is set as $\#p \ td \ b3lyp/6-31g^*$, which runs a calculation at $B3LYP/6-31G^*$ level by using the TDDFT method.

When the calculation is completed, find the related information about "Excited State 1" in the output \star .log file in order to find the vertical excitation energy and transition dipole moment (absorption) at the optimized S₀ geometry. In this example, the information is listed below:

Ground	to excited s	tate trans	ition elec	ctric dipole	moments	s (Au):	
state	Х	Y	Z	Dip. S.	Osc	•	
1	-4.6693	-0.0118	0.0112	21.8029	1.782	6	
Excited Sta	ate 1: Singlet-	A 3.3372 eV	371.52 nm	f=1.7826 <s**2< td=""><td>2>=0.000</td><td>75 -> 76</td><td>0.70728</td></s**2<>	2>=0.000	75 -> 76	0.70728
This state for optimization and/or second-order correction.							
Total Energy, $E(TD-HE/TD-KS) = -848,655200149$							

Hence, the vertical excitation energy at the optimized S_0 geometry is 3.3372 eV, and the transition dipole moment (absorption) can be obtained using Dip. S.:

 $\sqrt{21.8029} \times 2.54$ Debye = 11.86 Debye

7.4 Optimization calculation on lowest singlet excited state (S₁)

With the optimized S_0 geometry at hand, we can start optimizing S_1 geometry using the optimized S_0 geometry as the initial structure. The route section is set as $\#p \ td \ opt \ b3lyp/6-31g*$, which indicates an optimization at the B3LYP/6-31G* level using TDDFT method.

When the calculation is completed, locate the **last line with "SCF Done**" in the output *.log file in order to find single point energy at the optimized S_1 geometry. In this example, the last line with

"SCF Done" is the following:

```
SCF Done: E(RB3LYP) = -849.165742659 A.U.
```

Complete results can be found in directory tests/DSB/opt and frequency.

7.5 Frequency calculation at the optimized S₁ geometry

After finding the optimized S_1 geometry, we need to verify the optimization result and calculate its force constant matrix *via* frequency calculation. The route section is set as #p td freq b3lyp/6-31g*, which runs a frequency calculation at the B3LYP/6-31G* level using TDDFT method. You have to define the location of *.chk file in Link 0 Commands as well.

Use Gaussian built-in command formchk to generate a *.fchk file based on output *.chk. The *.fchk file contains readable force constant matrix information that is needed in dushin calculation.

The complete results can be found in directory tests/DSB/opt_and_frequency.

7.6 Transition dipole moment (emission) at the optimized S₁ geometry

Transition dipole moment (emission) and vertical excitation energy at the optimized S_1 geometry are also given when the calculation in section 7.4 is done. Find the relative information about "Excited State 1" in the output *.log file in order to locate the vertical excitation energy and transition dipole moment (emission) at the optimized S_1 geometry. In this example, the information is listed below:

Ground	to excited	state trans	ition elec	tric dipole	moments	(Au):
state	Х	Y	Z	Dip. S.	Osc.	
1	-5.3165	-0.0242	0.0000	28.2653	1.9597	,

Excited State 1: Singlet-?Sym 2.8300 eV 438.11 nm f=1.9597 <S**2>=0.000 75 -> 76 0.71066 This state for optimization and/or second-order correction.

Total Energy, E(TD-HF/TD-KS) = -849.061743778

Hence, vertical excitation energy at the optimized S_1 geometry is 2.8300 eV, and transition dipole moment (emission) can be obtained using Dip. S.:

 $\sqrt{28.2653} \times 2.54$ Debye = 13.50 Debye

The complete results can be found in directory tests/DSB/opt_and_frequency.

7.7 Adiabatic energy difference between S₀ and S₁ states

The adiabatic energy difference between S_0 and S_1 states can be calculated using single point energy results from sections 7.1 and 7.4.

In this example, the adiabatic energy difference is:

(-849.06174378+849.17423899)×27.2114 eV=3.0122 eV

7.8 Transition electric field and NACME at the optimized S₁ geometry

After finding the optimized S_1 geometry, we can calculate transition electric field at this geometry. Then it's possible to run a dushin calculation with NACME option toggled on.

The route section is set as the following line:

```
#p td b3lyp/6-31g(d) prop=(fitcharge,field) iop(6/22=-4, 6/29=1, 6/30=0, 6/17=2)
```

When the calculation is completed, copy two output *.log files into a new directory. One is transition electric field *.log file, which is obtained in this section. The other is frequency calculation at the optimized S_0 geometry *.log file, which is obtained in section 7.2. Then use get-nacme to start calculating NACME.

The complete results can be found in directory tests/DSB/nacme.

Part two: Transport Properties

8. Transport: Background

8.1 Charge Transfer Rate

Due to the weak coupling between molecules, the charge transport in most organics is dominated by the hopping mechanism, which implies that the transport dynamics can be decomposed into elementary charge transfer processes between different pairs of molecules. ^[1] The charge transfer between two molecules, M_i and M_j , is a charge exchange reaction. The initial and final states are M'_iM_j and $M_iM'_j$, where M' denotes the charge on molecule M. The widely used charge transfer rate from the classical Marcus theory reads^[2]

$$k_{ij} = \frac{V_{ij}^2}{\hbar} \sqrt{\frac{\pi}{\lambda k_B T}} \exp\left[-\frac{\left(\lambda + \Delta G_{ij}^0\right)^2}{4\lambda k_B T}\right]$$

Here, V_{ij} is the transfer integral between the initial and final states, λ is the reorganization energy which is defined as the energy change associated with the geometry relaxation during the charge transfer, and ΔG_{ij}^0 is relevant change of total Gibbs free energy. In molecular semiconductors with only one kind of molecules, ΔG_{ij}^0 equals to zero, and then the Marcus rate becomes

$$k_{ij} = \frac{V_{ij}^2}{\hbar} \sqrt{\frac{\pi}{\lambda k_B T}} \exp\left(-\frac{\lambda}{4k_B T}\right)$$

Thereby, the charge transfer is actually a thermal activation process over a barrier of $\lambda/4$. The Marcus rate is most appropriate when (1) the temperature is high, (2) the molecules are in equilibrium in both the initial and final states, and (3) the intermolecular diabatic couplings are weak.^[3]

8.2 Pauli Master Equation

When the charge transfer rates are defined, the charge transport dynamics can be characterized by the Pauli master equation (PME) with a Markov assumption. ^[4] It describes the time evolution of the electron population on each state with a set of purely classical kinetic equations,

$$\dot{P}_i = \sum_{j \neq i} \left(k_{ji} P_j - k_{ij} P_i \right)$$

where P_i is the occupation number of the charge to be on molecule *i*, and k_{ij} is the charge transfer rate from molecule *i* to *j*. Namely, the population change on state *i* is the difference between the total

population transfer from other states to state i and that from state i to other states. The PME can be solved directly through an iterative numerical scheme. One needs to set the initial populations on all states and solve the differential equations to get the charge distribution at any time t. Alternatively, one may use a kinetic Monte Carlo (KMC) algorithm with a series random walk trajectories. ^[5] In comparison, the KMC approach is numerically more efficient for large systems as converged results can be generally obtained with a sampling of acceptable number of trajectories.

8.3 Monte Carlo Simulation

The concept of Monte Carlo was first proposed by Stanislaw Ulam in the 1940s. Ulam was a mathematician who worked on the Manhattan Project. Initially, the method was derived to solve the problem of determining the average distance neutrons would travel through various materials. The method was named after the Monte Carlo Casino in Monaco since the randomness of the outcomes that is crucial to games such as roulette or dices is essential for Monte Carlo simulations.

The main ideas behind the Monte Carlo simulation are the repeated random sampling of inputs of the random variable and the aggregation of the results. The variable with a probabilistic nature is assigned a random value. The model is then calculated based on the random value. The result of the model is recorded, and the process is repeated. Usually, the process is repeated hundreds or thousand times. When the simulation is complete, the results can be averaged to determine the estimated value.

8.4 Lattice Random Walk

Random walk is a typical kind of Monte Carlo process. Using a regular lattice as an illustration, at each step the location jumps to another site according to some probability distribution. In a *simple random walk*, the location can only jump to neighboring sites of the lattice, forming a *lattice path*, as show in Figure 1.



Figure 8-1. Three representative random walks in three dimensions.

For a particle in a known fixed position at t = 0, the central limit theorem tells us that after a large number of independent steps in the random walk, the walker's position is distributed according to a normal distribution of total *variance*:

$$\sigma^2 = \frac{t}{\delta t}\varepsilon^2,$$

where *t* is the time elapsed since the start of the random walk, ε is the size of a step of the random walk, and δt is the time elapsed between two successive steps. This corresponds to the Green function of the diffusion equation that controls the Wiener process, which suggests that, after a large number of steps, the random walk converges toward a Wiener process (a stochastic process with similar behavior to Brownian motion, sometimes the Wiener process is called "Brownian motion"). In three dimensions, the *variance* corresponding to the Green's function of the diffusion equation is:

$$\sigma^2 = 6Dt$$

By equalizing this quantity with the variance associated to the position of the random walker, one obtains the equivalent diffusion coefficient to be considered for the asymptotic Wiener process toward which the random walk converges after a large number of steps:

$$D = \frac{\sigma^2}{2nt} = \frac{\varepsilon^2}{2n\delta t}$$

where n = 1, 2, or 3 is the dimensionality of the system under investigation.

8.5 Charge Carrier Mobility

The mobility of a charge carrier is related to the diffusion coefficient by the *Einstein* relationship:

$$\mathbf{D} = \frac{\mathbf{k}_B \mathbf{T}}{q} \, \mu \, .$$

Rearrange the above equation, we have:

$$\mu = \frac{q}{\mathbf{k}_B \mathbf{T}} \mathbf{D} \,.$$

Thus, the task is to first find the diffusion coefficient of a charge carrier, then the mobility of charge carrier is obtained by using the *Einstein* relationship. ^[1] To fulfil the task, we can resort to Monte Carlo simulations. In detail, an arbitrary molecular site in the bulk system is initially chosen as the starting position for the charge. The charge then has a probability of p_i to hop to the *i*-th neighbor (see Figure 2). In practice, in order to determine the next site of the charge in a statistical sense, a random number ξ uniformly distributed between 0 and 1 is generated. If $\sum_{i=1}^{b-1} p_i < \xi < \sum_{i=1}^{b} p_i$, the charge hops to the *b*-th neighbor with a hopping time $1/k_b$, which assumes no correlation between the hopping events along different pathways. The simulation continues until the diffusion distance exceeds the lattice constant by at least 2 – 3 orders of magnitude. This process is repeated for thousands of times and averaged to get a linear relationship between the mean-square displacement (MSD) and the simulation time.



Figure 8-2. Schematic representation of the charge hopping pathways from molecule A to its neighbors with probabilities $p_1, p_2, ..., and p_N$.

The diffusion coefficient D is calculated through

$$\mathbf{D} = \frac{1}{2n} \frac{dMSD}{dt} \,.$$

where n = 1, 2, or 3 is the dimensionality of the system under investigation.

In MOMAP Transport package, we setup a lot of initial different (random) seeds, record the tracks, and then average over the tracks. Even though an individual track looks rather jittery, however, when a certain number of (say 2,000) tracks are averaged, we can get a pretty linear averaged line (thick red line), as shown in the following figure:



Figure 8-3. Mobility calculation by using Monte Carlo simulations.

With the averaged track, we can fit to a linear line, obtain the diffusion coefficient, and then the charge carrier mobility.

References

- L. J. Wang, G. J. Nan, X. D. Yang, Q. Peng, Q. K. Li, and Z. Shuai, Chem. Soc. Rev. 39, 423-434 (2010).
- 2. R. A. Marcus, Rev. Mod. Phys. 65, 599-610 (1993).
- 3. S. H. Lin, C. H. Chang, K. K. Liang, R. Chang, Y. J. Shiu, J. M. Zhang, T. S. Yang, M. Hayashi, and F. C. Hsu, Adv. Chem. Phys. 121, 1 (2002).
- 4. H. J. Kreuzer, Nonequilibrium Thermodynamics and Its Statistical Foundations (Oxford University Press, New York, 1981).
- 5. X. D. Yang, L. J. Wang, C. L. Wang, W. Long, and Z. Shuai, Chem. Mater. 20, 3205-3211 (2008).

9. Transport: Quick Start

We assume that MOMAP is properly installed and configured for your site, you can edit your .bashrc if you are using Bash in Linux.

This chapter is intended for the novice user in using the program package, especially the MOMAP Transport sub-package. We will use the example of Naphthalene to show which steps are necessary to prepare a calculation and run the MOMAP transport calculations. In the meantime, we will give all important information in a consistent way.

9.1 Naming conversions

Before we begin with our first introductory example, we describe the naming conventions, to which we will abide by throughout this user's guide.

On UNIX-like systems the files are case-sensitive, when running MOMAP it is required that all files reside in a subdirectory ./test1. Thus, if we want to remove the calculations, we can easily delete the whole directory, or run the script transport clear.sh under the directory.

9.2 Create a new calculation

As mentioned above, we first create a sub-directory test1, and copy the file naphthalene.cif under test1. The naphthalene unit cell is shown in Figure 9-1.



Figure 9-1 Naphthalene unit cell

Use an editor or any handy command, we can see the crystal structure parameters in the first few lines of naphthalene.cif, some things like the following:

```
[test1]$ cat naphthalene.cif
data naphthalene
_audit_creation date
                                 2017-03-25
_audit_creation method
                                'Materials Studio'
_symmetry_space_group name H-M 'P1'
_symmetry_Int_Tables_number 1
 symmetry cell setting
                               triclinic
loop
_symmetry_equiv_pos as xyz
 х,у, z
_cell_length_a
                               8.0980
_cell_length_b
                               5.9530
\_cell\_length\_c
                               8.6520
_cell_angle_alpha
                              90.0000
_cell_angle beta
                              124.4000
cell angle gamma
                              90.0000
```

It is clear that the cif file is an output of Materials Studio with space group of 'P1', currently MOMAP Transport program can support all space groups, not restricted only to space group 'P1'. With a cif file, we have all the crystal structure parameters in hand, as shown above.

Now we have prepared our first molecular file, however, before we can run the MOMAP Transport calculations, we have to prepare the momap.inp file, a control file for MOMAP package.

There exist quite a few of control parameters for momap.inp, however, all the parameters have their default values if we do not set them. To make life easy, we have written a program called transport_geninp.exe to generate the momap.inp for the MOMAP transport calculations. Before we begin to generate the momap.inp, we would better setup our environment settings, as these settings rarely change in a specific computing cluster environment. The typical environment settings are as follows (you may put them in ~/.bashrc):

```
export MOMAP_JOB_SCHED=slurm
export MOMAP_JOB_QUEUE=X12C
export MOMAP_QC_EXE=g09
export MOMAP_QC_PPN=12
export MOMAP_MODULE_QC=gaussian/g09.e01
```

These are the initial values that will be entered into our momap.inp if we run the transport_geninp.exe, we can change them later on with an editor. The currently supported scheduling systems include PBS, SLURM, LSF and LOCAL, these are the scheduling systems in frequent use. The LOCAL means the jobs are run in a local machine, it can be of great help for a Linux box without job scheduling system. If needed, more scheduling systems can be added. If the computing cluster is installed with environment module, the last two lines can be added, but we can change the contents according to our specific situation.

If our quantum calculation (QC) engine is of the Gaussian g16, we need to change the third line to g16, and the fifth line to g16.b01.

Once the MOMAP environments are set, we can use our transport_geninp.exe to generate momap.inp, all the MOMAP Transport programs have a help option, either -h or --help, for example, in case transport_geninp.exe, we have:

```
[test1]$ transport geninp.exe --help
                                        * MOMAP Transport Calculation Utility, Version 2022A (2.3.3) build on Apr 24 2022 *
  Zhigang Shuai Group, Department of Chemistry, Tsinghua University, Beijing
*****
                                              Transport Momap Input Generation
Usage: transport_geninp.exe [opts]
 -config s : set config file, default to momap.inp
      : use cif file as molecule input (default)
: use mol file as molecule input
 -cif
 -mol
 -module : set to use environment module flag
 -terse : generate terse momap.inp (default)
 -verbose : generate verbose momap.inp
 -oldconfig: generate old config.inp
 -orca : use ORCA compute engine
-qchem : use Q-Chem compute engine
 -qchem
e.g.: transport geninp.exe
 transport_geninp.exe -config momap.inp
 transport_geninp.exe -verbose
 transport geninp.exe -cif
 transport geninp.exe -mol
 transport geninp.exe -module
 transport_geninp.exe -config momap.inp -verbose
 transport_geninp.exe -oldconfig
 transport geninp.exe -orca
```

If option -config is used, then we can designate our output control file, the default file is momap.inp if this option is not specified.

If option -cif is used, then cif crystal parameter will be used in momap.inp, it will automatically search for the first found cif file in the current directory if it exists.

If option -mol is used, then mol molecule parameter will be used in momap.inp, again it will automatically search for the mol files in the current directory.

If option -module is used, then it will activate module parameter output.

If option -terse is used, then it will generate a *terse* momap.inp, while the other parameters using the default values.

If option -verbose is used, then it will generate a *verbose* momap.inp, almost all the parameters will be entered into the momap.inp. Thus, we can tune the parameters as needed.

These options can be used in combination, as shown in the last line.

If we run the transport_geninp.exe without any options, it will generate a momap.inp like the following:

```
[test1]$ cat momap.inp
&transport
 do_transport_prepare
                                           = 1
 do_transport_submit_HL_job
                                           = 1
 do_transport_get_transferintegral = 1
do_transport_submit_RE_job = 1
 do_transport_get_re_evc
                                           = 1
                                           = 1
 do_transport_run_MC
 do_transport_get_mob_MC
                                           = 1
 do_transport_run_MC_temp
                                           = 0
 do_transport_get_mob_MC_temp
                                          = 0
 do transport run ME
                                           = 0
                                           = 0
 do_transport_get_mob_ME
 do_transport_run_ME_temp
                                           = 0
 do_transport_get_mob_ME_temp
do_transport_gathordata
                                           = 0
 do transport gatherdata
                                           = 1
 # Job Scheduling
 sched_type = pbs ! pbs, slurm, lsf, or local
queue_name = blade
 compute_engine = 1
                                 ! 1 = Gaussian, 2 = ORCA, 3 = Q-CHEM
                    = g09 ! g09/g16 or fullpath/orca or qchem
 qc exe
# module qc
                    = gaussian/g09.e01
 qc_method= b3lypqc_basis= b3lyp STO-3gqc_basis_re= b3lyp STO-3gqc_memory= 4096 ! MBqc_nodes= 1
 qc_nodes
                     = 8
 qc ppn
 # Temperature Dependence
        = 300
 temp
 start_temp = 200
end_temp = 300
delta_temp = 50
ratetype = marcus ! marcus or quantum
lat_cutoff = 4 ! for neighbor list construction
                    = 2000
 nsimu
                    = 1000 ! in ns
 tsimu
                    = 5
 tsnap
 crystal
                     = naphthalene.cif
```

Other control parameters can be entered into momap.inp, users are advised to consult the file data/config.inp for details.

For example, users may add a line like the following to momap.inp: nodelist = "c01,c02"

to designate the computing nodes to be used in the running.

```
In addition, the transport_prepare.exe can also be used to prepare oniom input files, for
example, if we set the 3<sup>rd</sup> bit up for control parameter data_mol_output_level, that is,
data_mol_output_level = 8
Then, after running transport_prepare.exe, we have 4 extra files in data directory:
mol1_oniom.com
mol1_oniom.xyz
mol2_oniom.com
```

The MOMAP Transport package uses the following control block:

```
&transport
...
/
It starts with &transport, and ends with /.
```

```
The lines beginning with '#' are comments, the '!' is also used for comment as in the case of Fortran coding.
```

The initial do_lines are control flags, can be either 1 (enabled) or 0 (disabled). If we need to do MC calculations, we simply set them to 1 accordingly.

With the generated momap.inp, we can do some fine tunings for our specific case, for example, we may change queue name value from blade to X12C, gaussian ppn from 16 to 12 *etc*.

In the meantime, a file called run.sh is also generated, it contains:

```
[test1]$ cat run.sh
#!/bin/sh
python $MOMAP ROOT/bin/momap.py &> momap.log &
```

Once we have carefully checked the momap.inp, we can simply run the run.sh by issuing:

```
[test1]$ sh run.sh
```

Or

```
[test1]$ python $MOMAP_ROOT/bin/momap.py &> momap.log &
```

In the meantime, we can check the running processes by looking into the momap.log file, or the RUN directory where the running locks are located. We may also use the job scheduling commands to check the running processes.

If everything is okay, at the end of the log file, we can see somethings like the following:

will appear, which means the job is done successfully.

Please carefully check the momap.log file for any abnormalities.

Finally, the output results are gathered and put in file momap.dat.

10. Transport: Looking into the details

The momap.py is the job manager for MOMAP package, we can see the various running steps in the momap.log file. Now we have a look into the detailed processes of MOMAP Transport calculations.

10.1 Transport preparation

The first step of job manager momap.py is to run transport_prepare.exe. When the transport_prepare.exe is run, it will generate quite a few of directories and files. To demonstrate how the data and directories are arranged for MOMAP transport calculations, we set both control parameters HL_unique_mol and RE_unique_mol to 0 in the momap.inp.

By running the transport prepare.exe, the screen output is as follows:

```
$ transport prepare.exe
***** Perform Transport Preparation ...
Reading config file "momap.inp"...
Reading crystal file "naphthalene.cif"...
 Identifier:
 Spacegroup name: 'P1'
 Spacegroup operations:
   X, Y, Z
 Cell lattice a = 8.098
 Cell lattice b = 5.953
 Cell lattice c = 8.652
 Cell lattice alpha = 90
 Cell lattice beta = 124.4
 Cell lattice gamma = 90
 natoms cif = 36
 First atom: C1 C 0.082321 0.018562 0.328357
 . . .
 Last atom: H36 H 0.466698 0.795196 0.331298
 Unit cell nmols = 2
 Unit cell natoms = 18 18
Crystal file naphthalene.cif parsing done.
Make whole molecules...
 molecule 1 COM = 0.000000 0.000000 -0.000000
 molecule 2 COM = 0.500000 0.500000 1.000000
Writing config file "data/config.inp"...
**** MOMAP Build Neighbor List ****
 Neighbor rcutoff distance: 4
 Neighbor search cell (-/+): 3 3 3
**** End of MOMAP Build Neighbor List ****
***** MOMAP Transport Preparation Successfully Done.
```

Then, all the necessary data and directories for MOMAP Transport calculations are prepared. The full directory and file tree is shown in the following pages (in Linux case, as follows, by simply run the tree command):

. / L	
	data
	— cellvec.dat
	- config.inp
	- moll bonds.dat
	mol1.mol
	moll neighbors.cif
	- moll neighbors mid.cif
	- mol2 bonds.dat
	mol2.mol
	mol2 neighbors.cif
	mol2 neighbors mid.cif
	- neighbor.dat
	re lambda 4P files-e.dat
	relambda 4P files-h.dat
	- trans int files.dat
	uc H.inp
	Luc_L.inp
	evc
	- moll
	elec
	job get NM.local
	hole
	job get NM.local
	mol2
	elec
	job get NM.local
	Lhole
	🖵 job get NM.local
	HL — —
	2mol-1-10.com
	2mol-1-11.com
	2mol-1-12.com
	2mol-1-13.com
	2mol-1-14.com
	2mol-1-1.com
	2mol-1-2.com
	2mol-1-3.com
	2mol-1-4.com
	2mol-1-5.com
	2mol-1-6.com
	2mol-1-6.com 2mol-1-7.com
	2mol-1-6.com 2mol-1-7.com 2mol-1-8.com
	2mol-1-6.com 2mol-1-7.com 2mol-1-8.com 2mol-1-9.com
	2mol-1-6.com 2mol-1-7.com 2mol-1-8.com 2mol-1-9.com 2mol-2-10.com
	2mol-1-6.com 2mol-1-7.com 2mol-1-8.com 2mol-1-9.com 2mol-2-10.com 2mol-2-11.com
	2mol-1-6.com 2mol-1-7.com 2mol-1-8.com 2mol-1-9.com 2mol-2-10.com 2mol-2-11.com 2mol-2-12.com
	2mol-1-6.com 2mol-1-7.com 2mol-1-8.com 2mol-1-9.com 2mol-2-10.com 2mol-2-11.com 2mol-2-12.com 2mol-2-13.com
	2mol-1-6.com 2mol-1-7.com 2mol-1-8.com 2mol-1-9.com 2mol-2-10.com 2mol-2-11.com 2mol-2-12.com 2mol-2-13.com 2mol-2-14.com
	2mol-1-6.com 2mol-1-7.com 2mol-1-8.com 2mol-1-9.com 2mol-2-10.com 2mol-2-11.com 2mol-2-12.com 2mol-2-13.com 2mol-2-14.com
	2mol-1-6.com 2mol-1-7.com 2mol-1-8.com 2mol-1-9.com 2mol-2-10.com 2mol-2-11.com 2mol-2-12.com 2mol-2-13.com 2mol-2-14.com 2mol-2-1.com
	2mol-1-6.com 2mol-1-7.com 2mol-1-8.com 2mol-2-10.com 2mol-2-11.com 2mol-2-13.com 2mol-2-14.com 2mol-2-1.com 2mol-2-2.com 2mol-2-3.com
	2mol-1-6.com 2mol-1-7.com 2mol-1-8.com 2mol-2-10.com 2mol-2-11.com 2mol-2-13.com 2mol-2-14.com 2mol-2-2.com 2mol-2-3.com
	2mol-1-6.com 2mol-1-7.com 2mol-1-8.com 2mol-2-10.com 2mol-2-11.com 2mol-2-12.com 2mol-2-13.com 2mol-2-14.com 2mol-2-2.com 2mol-2-3.com 2mol-2-4.com
	2mol-1-6.com 2mol-1-7.com 2mol-1-8.com 2mol-2-10.com 2mol-2-11.com 2mol-2-13.com 2mol-2-14.com 2mol-2-2.com 2mol-2-3.com 2mol-2-4.com 2mol-2-5.com
	2mol-1-6.com 2mol-1-7.com 2mol-1-8.com 2mol-2-10.com 2mol-2-11.com 2mol-2-13.com 2mol-2-14.com 2mol-2-2.com 2mol-2-3.com 2mol-2-3.com 2mol-2-5.com 2mol-2-6.com
	2mol-1-6.com 2mol-1-7.com 2mol-1-8.com 2mol-2-10.com 2mol-2-11.com 2mol-2-13.com 2mol-2-14.com 2mol-2-2.com 2mol-2-3.com 2mol-2-3.com 2mol-2-5.com 2mol-2-6.com
	2mol-1-6.com 2mol-1-7.com 2mol-1-8.com 2mol-2-10.com 2mol-2-11.com 2mol-2-13.com 2mol-2-14.com 2mol-2-2.com 2mol-2-3.com 2mol-2-3.com 2mol-2-5.com 2mol-2-6.com 2mol-2-8.com

Cont.

nei_mol-1-10.com
nei mol-1-11.com
nei mol-1-12 com
nei_mol-1-13.com
nei mol-1-14.com
nei mol-1-1.com
nei_mol-1-3.com
nei mol-1-4.com
nei_mol-1-5.com
nei_mol-l-/.com
nei mol-1-8.com
nei mol-1-9.com
- neimol-2-10 com
nei_moi-2-ii.com
- nei_mol-2-12.com
nei mol-2-13.com
- neimol-2-14 com
nei_mol-2-2.com
nei mol-2-3.com
here nei mol-2-4.com
nei_mol-2-6.com
nei_mol-2-7.com
nei mol-2-8.com
nei_mol-2-9 com
uc_mol-2.com
jobs
ich 2mol-1.pbs
job_nei_mol-l.pbs
job nei mol-2.pbs
job_re-moll-anion.pbs
ich_ro_moll_cation_phs
Job_re-moli-neutral.pbs
job_re-mol2-anion.pbs
job_re-mol2-cation.pbs
ich_re_mol2_neutral_nbs
Job_transint.pbs
job_uc_mol.pbs
MC-marcus
L — get mob pbs
get_mob.py
prepare-mc.py
run mc batch.py
get_mob.pbs
get_mob.py
prepare-mc.pv
run_mc.pos
mol1.mol
mol2.mol
— moman inn
I mondy the

Cont.



If control parameter sched_job_array=0 is set in momap.inp, more job scripts will be generated. However, do not be frightened by the sheer number of files, as they are all well-organized.

In data directory, the uc_H.inp and uc_L.inp, input files for HOMO and LUMO determinations, are for internal use only, and may be used to check the correctness of the results. The mol1.mol and mol2.mol are the separated molecular files of a cif file, for example, also can be used to check the correctness of molecule separation.

The file reorg_einternal_files.dat is used for reorganization internal energy calculations for molecules in the unit cell, which is used for the onsite energy calculation if the control parameter lat_site_energy (default to 0) is set to 1 in the momap.inp control file.

The trans_int_files.dat is for transfer integral calculations. The other files have the meaning as the name suggests.

Finally, the config.inp is the configuration file that the system actually uses. In the default settings, we use scheduling job array (sched_job_array = 1), do not include onsite energy (lat_site_energy = 0), output only base mobility plus angular resolved mobilities information (mob_output_level = 2).

For example, if we do not want to output angular resolved mobilities, we can unset the 2^{nd} bit $(mob_output_level$ is a bit-wise setting flag), that is, $mob_output_level = 0$. The parameter data_mol_output_level is used to control the output of molecular information in data directory, default to 2. It is a bit-wise control parameter, the 1^{st} bit corresponding to output for the 1^{st} molecule, 2^{nd} bit to output for all molecules, 3^{rd} bit to output for the supercell cif file, and 4^{th} bit to output for the Gaussian oniom input files. All the bit setting can be combined, for example, to output all information, we can set the parameter to 1+2+4+8 = 15, that is , data mol output level = 15.

The evc directory is a work directory for reorganization energy related calculations, which uses data from the RE directory to do the calculations.

The HL directory is for transfer integral calculations. The naming convention is as follows:

- The "uc_mol-" prefix is for single molecule in the central unit cell, thus the uc_mol-1.com and uc mol-2.com are two Gaussian input files for the central unit cell.
- The "nei_mol-" prefix is for single molecule in the neighbor unit cells, say, nei_mol-1 com means the 6th neighbor molecule (the specific cell index is specified in the neighbor.dat file) of the 1st molecule in the central unit cell.
- The "2mol-" prefix is for two-molecule-pair (dipole), say, 2mol-1-12.com, which means the 1st molecule in the central unit cell and the 12th neighbor molecule of this 1st molecule in central cell are combined to form the Gaussian input file.

The jobs directory is used for QC (Gaussian) calculations in directories HL and RE, we use scheduling job array option as the default option to reduce the number of job scripts, which is controlled by the control parameter sched job array. These job scripts are called by the python

scripts in scr directory.

The RE directory is for reorganization calculations. The control files for evc.exe are also put in this directory. The normal mode calculations are done with these three directories, that is, evc, RE, and scr.

The RUN directory is a directory where the running locks are put, users can check this directory for system progress. If an error occurs, ERROR flag will be set up in the RUN directory, which can be used to trace where the error occurs.

The scr directory is a directory where the python scripts are put, these python scripts are called by the job manager momap.py. The sequential executions are logged into the momap.log, for example, if the output is redirected to momap.log.

The logging information for transport_prepare.exe may looks like some things as follows:

```
Do transport preparation ...
>> Run at directory: .
$> transport_prepare.exe
***** Perform Transport Preparation ...
Reading config file "momap.inp" ...
Reading crystal file "150h.cif" ...
 Cell lattice a = 5.9575
 Cell lattice b = 7.4678
 Cell lattice c = 38.764
 Cell lattice alpha = 90
 Cell lattice beta = 90.067
 Cell lattice gamma = 90
 natoms cif = 92
 First atom: C1 C 0.09200 0.35760 0.02220
 . . .
 Last atom: H92 H 0.15250 0.78170 0.41950
 Unit cell nmols = 2
 Unit cell natoms = 46 46
Crystal file 150h.cif parsing done.
Writing config file "data/config.inp" ...
**** MOMAP Build Neighbor List ****
 Neighbor rcutoff distance: 7
 Neighbor search cell (-/+): 3 3 3
**** End of MOMAP Build Neighbor List ****
***** MOMAP Transport Preparation Successfully Done.
--- Normal end for transport preparation.
```

In the logging file, we can see where the job is run and what job is run.

From the above logging information, we know the job is run at the current working directory. (dot) (note the line begins with >>), the job run is transport_prepare.exe (note the line begins with \$>).

Finally, if the command is run successfully, at the end of logging information for this program, there will appear a line, like, "--- Normal end for transport preparation".

There may be other information which may be useful to users in the logging file.

However, to ensure the computing efficiency, in actual calculations, we normally set both control parameters HL unique mol and RE unique mol to 1, which is also the default setting.

Note that users may tune the parameter bond_dis_scale (default to 1.15) when molecular separation with cif file is failed.

Now, by running the transport prepare.exe, the screen output is as follows:

```
[test1]$ transport prepare.exe
***** Perform Transport Preparation ...
Reading config file "momap.inp" ...
Reading molecular file "mol1.mol" ...
Reading molecular file "mol2.mol" ...
Writing config file "data/config.inp" ...
Crystal file naphthalene.cif parsing done.
Make whole molecules...
 molecule 1 COM = 0.000000 0.000000 -0.000000
 molecule 2 COM = 0.500000 0.500000 1.000000
Writing config file "data/config.inp"...
**** MOMAP Build Neighbor List ****
 Neighbor rcutoff distance: 4
 Neighbor search cell (-/+): 3 3 3
**** End of MOMAP Build Neighbor List ****
*** Check Duplicate 2mol pairs ***
 Unique 2mol pairs: 5 out of 28
    1 1
1 5
          <=>
                  1
          <=>
                  5
       7
                 7
     1
          <=>
     1 11 <=> 11
    1 13
           <=>
                13
*** End of Check Duplicate 2mol pairs ***
**** Check RE Duplicate Molecules in Unit Cell ****
 Unit cell molecule indexes: 1 1
 Unit cell unique molecule indexes: 1
**** End of Check RE Duplicate Molecules in Unit Cell ****
**** Check HL Duplicate Molecules in Unit Cell ****
 Unit cell molecule indexes: 1 1
 Unit cell unique molecule indexes: 1
**** End of Check HL Duplicate Molecules in Unit Cell ****
***** MOMAP Transport Preparation Successfully Done.
```

Here, only the unique molecules and molecular pairs (dipoles) are selected for the transfer integral

and reorganization energy calculations, which greatly reduces the computing time for QC job calculations. The full directory and file tree is shown as below:



Cont.

RE
evc-e-mol1.inp
evc-h-mol1.inp
re-moll-anion.com
re-moll-anion_nC.com
re-moll-cation.com
re-moll-cation nC.com
re-mol1-neutral.com
re-moll-neutral_eN.com
- re-mol1-neutral_hN.com
RUN
run.sh
L scr
— copy_RE_lambda_4P_files.py
— gaussian_log_check.py
get_RE_lambda_4P.py
get_RE_lambda_evc.py
get_RE.py
get_transint.py
merge_evc_NM_output.py
mol_one_nei.py
mol_one_uc.py
<pre>mol_RE_anion_cation.py</pre>
mol_RE_lambda_4P.py
<pre> mol_RE_neutral.py</pre>
mol_two.py
momap.sh
prepare_RE.py
L run_RE.py
13 directories, 76 files

As we only calculate the *unique* molecules and molecular pairs (dipoles), we need to map these unique molecules and molecular pairs to the original molecules and molecular pairs, the mapping information is put in file unique_id_map.dat under data directory:

<pre>[test1]\$ cat unique_id_map.dat # Unique ID mapping 2</pre>
2 1 15
2 2 16
2 3 17
2 5 19
2 6 20
2 7 21
2 8 22
2 9 23
2 10 24
2 11 25
2 12 26
2 13 27
2 14 28

The first line is comment, the 2nd line is the number of molecules in the central unit cell, then follows number of neighbors for each central unit cell molecule and ID mapping data, which repeats the number of molecules in the central unit cell. For the three-column data in the above table, the first column is the central unit cell molecule ID, the second column is the neighbor ID for the corresponding central unit cell molecule, and the third column is the *uniformly* numbered IDs for the whole central unit cell.

Thus, for example, a file 2mol-13. com has a uniform ID 13, which corresponds to central unit cell molecule ID 1 and neighbor molecule ID 13, as show in the above list. As another example, if we have a file 2mol-24. com, from the above list, we know it corresponds to the central unit cell molecule ID 2 and neighbor molecule ID 10.

10.2 Transfer Integral Calculations

Once the transport preparation is done, all the basic files and directories are created.

The next step is to do the transfer integral calculations.

The work is done by calling two python scripts in scr directory, that is, mol_one.py and mol_two.py, to do the one-molecule single point energy calculations and two-molecule single point energy calculations. These two python scripts set up running locks and submit jobs for the transfer integral calculations.

The logging information may look like the following:

```
Submit jobs for transfer integral calculations ...
>> Run at directory: .
$> python scr/mol_one.py
9486[].ntestq
9487[].ntestq
9488[].ntestq
$> python scr/mol_two.py
9489[].ntestq
--- Normal end for transfer integral calculations.
```

When a job is finished, it will remove the corresponding lock automatically.

10.3 Reorganization Energy Calculations

When the transfer integral calculations finish, all related locks on transfer integral calculations will be cleaned. The MOMAP manager will soon submit jobs for reorganization energy calculations. Comparing to the transfer integral calculations, this step takes more time to finish.

The logging information is as follows:

```
Submit jobs for reorganization energy calculation ...
>> Run at directory: .
$> python scr/mol_RE.py
9491.ntestq
9492.ntestq
--- Normal end for reorganization energy calculations.
```

Again, when a job is finished, it will remove the corresponding lock automatically.

More options can be added in this step. For example, if one would like to optimize the anion and cation state geometries based on the optimized neutral state geometry, one can set the parameter RE_use_neutral_chk to 1, that is, RE_use_neutral_chk = 1. Also, if one would like to calculate the reorganization energies by using the Nelson four-point method, one can set the

parameter RE_calc_lambda_4P to 1, that is RE_calc_lambda_4P = 1. This can be used to check if the reorganization energy in evc calculation is reliable.

10.4 Collect Transfer Integrals

In this step, by calling the python script scr/get_transint.py, we obtain the transfer integral data, VH.dat and VL.dat, for the later transfer hopping rate calculations.

The logging information can be some things as follows:

```
Collect transfer integrals ...
>> Run at directory: .
$> python scr/get_transint.py
9493[].ntestq
--- Normal end for collecting transfer integrals.
```

The above calculations actually use information listed in files trans_int_files.dat under data directory. For example, the contents of trans int files.dat may look as follows:

```
[test1]$ cat trans int files.dat
2
14
../HL/2mol-1.log ../HL/uc_mol-1.log ../HL/nei_mol-1.log 1 2
../HL/2mol-1.log ../HL/uc_mol-1.log ../HL/nei_mol-1.log 1 2
../HL/2mol-1.log ../HL/uc_mol-1.log ../HL/nei_mol-1.log 1 2
../HL/2mol-1.log ../HL/uc mol-1.log ../HL/nei mol-1.log 1 2
../HL/2mol-5.log ../HL/uc_mol-1.log ../HL/nei_mol-5.log 1 1
../HL/2mol-5.log ../HL/uc_mol-1.log ../HL/nei_mol-5.log
../HL/2mol-7.log ../HL/uc_mol-1.log ../HL/nei_mol-7.log
                                                                    1
                                                                       2
                                                                    1
../HL/2mol-7.log ../HL/uc mol-1.log ../HL/nei mol-7.log 1 2
../HL/2mol-7.log ../HL/uc mol-1.log ../HL/nei mol-7.log 1 2
../HL/2mol-7.log ../HL/uc_mol-1.log ../HL/nei_mol-7.log 1 2
../HL/2mol-11.log ../HL/uc_mol-1.log ../HL/nei_mol-11.log 1 1
../HL/2mol-11.log ../HL/uc_mol-1.log ../HL/nei_mol-11.log 1 1
../HL/2mol-13.log ../HL/uc_mol-1.log ../HL/nei_mol-13.log 1 1
../HL/2mol-13.log ../HL/uc mol-1.log ../HL/nei mol-13.log 1 1
14
../HL/2mol-1.log ../HL/uc_mol-1.log ../HL/nei_mol-1.log 2 1
../HL/2mol-1.log ../HL/uc_mol-1.log ../HL/nei_mol-1.log
                                                                    2
                                                                      1
../HL/2mol-1.log
                    ../HL/uc mol-1.log ../HL/nei mol-1.log
                                                                    2
                                                                       1
../HL/2mol-1.log ../HL/uc mol-1.log ../HL/nei mol-1.log
                                                                    2 1
../HL/2mol-5.log ../HL/uc mol-1.log ../HL/nei mol-5.log 2 2
../HL/2mol-5.log ../HL/uc_mol-1.log ../HL/nei_mol-5.log 2 2
../HL/2mol-7.log ../HL/uc_mol-1.log ../HL/nei_mol-7.log 2
../HL/2mol-7.log ../HL/uc_mol-1.log ../HL/nei_mol-7.log 2
../HL/2mol-7.log ../HL/uc_mol-1.log ../HL/nei_mol-7.log 2
                                                                       1
                                                                       1
                                                                       1
../HL/2mol-7.log ../HL/uc mol-1.log ../HL/nei mol-7.log 2 1
../HL/2mol-11.log ../HL/uc_mol-1.log ../HL/nei_mol-11.log 2 2
../HL/2mol-11.log ../HL/uc_mol-1.log ../HL/nei_mol-11.log 2 2
../HL/2mol-13.log ../HL/uc_mol-1.log ../HL/nei_mol-13.log
                                                                       2 2
../HL/2mol-13.log ../HL/uc mol-1.log ../HL/nei mol-13.log
                                                                       2 2
```

The first line contains the number of molecules in unit cell. Then follows a number of neighbors for that each molecule in the central unit cell, plus the three-file-group listing and the two molecular IDs. These files are used by the MOMAP command transport_transferintegral.exe.

10.5 Analyze Reorganization Energies

In this step, we further split the calculation into three parts: prepare_RE.py, run_RE.py, and get_RE.py. The first part is to prepare input files for the evc.exe program to do normal mode calculations, the second part is using the scheduling system to do the actual calculations, while the third part is to collect the calculated results and put the results into places.

The logging information may look as follows:

```
Analyze reorganization energies ...
>> Run at directory: .
$> python scr/prepare RE.py
Prepare for evc calculations ...
 treating mol01 ...
 treating molO2 ...
$> python scr/run RE.py
9494.ntestq
9495.ntestq
9496.ntestq
9497.ntestq
$> python scr/get RE.py
Calculating NM data ...
 treating mol01 ...
 treating molO2 ...
--- Normal end for analyzing reorganization energies.
```

10.6 Monte Carlo (MC) simulations

Once the above preparation work is done, we can do MC simulations to calculate the charge carrier mobilities.

This step is also split into two parts, that is, prepare-mc.py and run_mc_batch.py. The first part is to copy the obtained related input files (e.g., VH.dat, VL.dat, NM-e.dat NM-h.dat) into the MC working directory, and do the hopping rate calculations. The second part is to submit jobs to the scheduling (batching) system to do the MC simulations. As the MC program runs, the track files are written out into tracks directory. Normally, 2000 tracks will generate fairly good mobility results.

In this step, we normally take advantage of the OpenMP parallelization capability, it linearly scales with the number of cores in a node. For example, if the running node has 28 cores, the performance gain is 28 times comparing to the same serial job.

The logging information may look as follows:

```
Run Monte Carlo (MC) simulations ...
>> Run at directory: MC-marcus/elec
$> python prepare-mc.py
*** Perform Transport Hopping Rate Calculation ...
Reading config file "momap.inp" ...
Reading crystal file "naphthalene.cif" ...
*** Successfully done.
$> python run_mc_batch.py
9498.ntestq
>> Run at directory: MC-marcus/hole
$> python prepare-mc.py
*** Perform Transport Hopping Rate Calculation ...
Reading config file "momap.inp" ...
Reading crystal file " naphthalene.cif" ...
*** Successfully done.
$> python run_mc_batch.py
9499.ntestq
--- Normal end for Monte Carlo (MC) simulations.
```

The ratetype supported are Marcus, quantum, and egelst.

10.7 Calculate Random Walk Mobilities

Once the MC simulations finish, we can calculate the random walk mobilities from the MC track files by using the Einstein relationship.

The logging information is as follows:

```
Calculate Random Walk mobilities ...
>> Run at directory: MC-marcus/elec
$> python get_mob.py
9500.ntestq
>> Run at directory: MC-marcus/hole
$> python get_mob.py
9501.ntestq
--- Normal end for Random Walk mobilities.
```

Depends on the do_ options we selected, there may be temperature dependent MC simulations and mobility calculations, or ME related calculations, but the procedures are similar.

In the MC calculation directories, once the ps2png is properly installed, we can use the following commands to generate and display the 3D and 2D mobility plots:

\$> gnuplot *.gnu
\$> ps2png *.eps
\$> display *.png

If the installed gnuplot supports term pngcairo, we can simply run:











Fig. 10-1 The 3D and 2D plots for the electron case by using gnuplot

In addition, if numpy and matplotlib packages are installed with python, we can also use the generated python scripts to display the mobility plots. The corresponding python scripts in running MC directories are: mob_direction_all.py, mob_plane_xy.py, mob_plane_xz.py and mob_plane_yz.py. For example, the 3D and 2D plots for the electron case are shown as follows:



3D plot

Plane xy



Plane xz



Fig. 10-2 The 3D and 2D plots for the electron case by using matplotlib with python

10.8 Gather data

As all the calculations finish, the results are gathered to the file momap.dat as follows.

```
|\backslash/|
   | \rangle /
                                            Version 2022A (2.3.3)
 Copyright (c) 2017 Shuaigroup @ Tsinghua University &
        Institute of Chemistry, Chinese Academy of Sciences.
        All Rights Reserved.
Running configuration:
  data/config.inp
Separated molecular information:
  data/mol1.mol
  data/mol2.mol
Neighbor information:
  data/neighbor.dat
  data/mol1_neighbors.cif
data/mol2_neighbors.cif
Transfer integral information:
  data/VH.dat
  data/VL.dat
Reorganization energy information:
  data/NM-e.dat
  data/NM-h.dat
**** Hopping rates for MC-marcus/elec:
  MC-marcus/elec/hoprates.dat
**** Mobility data for MC-marcus/elec
mob_a / error [cm**2/Vs]: 6.283116e+00
mob_b / error [cm**2/Vs]: 4.462247e+00
                                                6.268443e-01
                                                4.881686e-01
mob<sup>c</sup> / error [cm**2/Vs]: 8.591702e-06
                                               7.566622e-07
mob_av / error [cm**2/Vs]: 3.581787e+00
                                                1.879785e-01
Directional mobilities are in file:
 MC-marcus/elec/mob direction all.dat
**** End of Mobility data for MC-marcus/elec
**** Hopping rates for MC-marcus/hole:
 MC-marcus/hole/hoprates.dat
**** Mobility data for MC-marcus/hole
mob_a / error [cm**2/Vs]: 5.832380e+00
                                               5.140441e-01
mob<sup>b</sup> / error [cm**2/Vs]: 5.071254e+00
                                               4.927727e-01
mob_c / error [cm**2/Vs]: 7.975353e-06
mob_av / error [cm**2/Vs]: 3.634544e+00
                                               6.495725e-07
                                                2.263642e-01
Directional mobilities are in file:
 MC-marcus/hole/mob_direction_all.dat
**** End of Mobility data for MC-marcus/hole
Normal end of MOMAP data gathering.
```

Finally, the job is done!

Part three: Accessories and Utilities

11. Transport: Parameters

11.1 Transport environment variables

•	MOMAP_ROOT	Must be set before running MOMAP!
•	MOMAP_LICENSE	If not set, then \$MOMAP_ROOT/license/hzwtec.lic is assumed.
•	MOMAP_SSH_PORT	(default to 22)
•	MOMAP_LICENSE_DEBUG	(default to FALSE, setting to TRUE will write license debug file
		<pre>'momap_lic_log.txt'under directory /tmp)</pre>
•	MOMAP_JOB_SCHED	Optional
•	MOMAP_JOB_QUEUE	Optional
•	MOMAP_QC_EXE	Optional
•	MOMAP_QC_PPN	Optional
•	MOMAP_QC_NODES	Optional
•	MOMAP_MODULE_QC	Optional

11.2 Transport input variables

do_transport_prepare	Default to 1, can be 0 (disable) or 1 (enable)
do_transport_submit_HL_job	Default to 1, can be 0 or 1
<pre>do_transport_get_transferintegral</pre>	Default to 1, can be 0 or 1
do_transport_submit_RE_job	Default to 1, can be 0 or 1
do_transport_get_re_evc	Default to 1, can be 0 or 1
do_transport_run_MC	Default to 1, can be 0 or 1
do_transport_get_mob_MC	Default to 1, can be 0 or 1
do_transport_run_MC_temp	Default to 0, can be 0 or 1
do_transport_get_mob_MC_temp	Default to 0, can be 0 or 1
do_transport_run_ME	Default to 0, can be 0 or 1
do_transport_get_mob_ME	Default to 0, can be 0 or 1
do_transport_run_ME_temp	Default to 0, can be 0 or 1
do_transport_get_mob_ME_temp	Default to 0, can be 0 or 1
do_transport_gather_momap_data	Default to 1, can be 0 or 1
sched_type	Scheduling type, can be pbs, slurm, lsf, or local.
queue_name	Scheduling queue name
sched_job_array	Default to 1, can be 0 or 1, if use job array in scheduling
module_qc	Default to empty, can be set to, e.g., gaussian/g16.c01-avx2
module_momap	Default to empty, can be set to, e.g., momap/2022A-mpich2
nodelist	Default to empty, can be, nodelist = " $c01$, $c02$ " to designate
	the computing nodes to be used.
job_slot_limit	Default to 0, means no limit to number of jobs at the same
	time.
walltime_hour	setting walltime in job submission scripts, default to 1000.
compute_engine	Default to 1, can be 1 (Gaussian), 2 (ORCA), 3 (Q-Chem)
qc_method	Default to "b31yp"
qc_basis	Default to "b3lyp STO-3g"
	Zindo calculation is supported by using "int=zindos" as
	input for qc_basis, can be used for large system
	calculations.
qc_basis_re	For reorganization calculation if set, otherwise default to

	qc_basis.
qc_exe	Default to g09
qc_memory	Default to 4096, in MB
qc_nodes	Default to 1
qc_ppn	Default to 8
scratch	Default to /tmp, only valid for ORCA calculation.
module_qc	Use module to setup QC running environment
start_temp	Default to 200
end_temp	Default to 300
delta_temp	Default to 50
chargetype	Default to a, can be e: electron, h: hole or a: all
evc_type	Default to cart, can be cart or int
use_evc_dint	Default to 0, if this variable is set to 1, then use dint to
	calculate reorganization energy.
vector_a	e.g., 8.098 0.0 0.0
vector_b	e.g., 0.0 5.975 0.0
vector_c	e.g., -4.888 0.0 7.138
lat_cutoff	Default to 4.0 angstroms
neighbor_scell	Default to 3 3 3, for neighbor cell search
super_cell	Default to 5 5 5, for ME calculations
lat_site_energy	Default to 0, for onsite energy calculations
momap_dat_file	Default to momap-{ratetype}.dat
mob_output_level	Default to 2, can be 0-base, 2-mob_all
delta_angle	Default to 10, for angular resolved mobility calculation.
data_mol_output_level	Default to 2 (set the 2 nd bit up)
	1 st bit – output only 1 st molecular data files, 2 nd bit – output
	all molecular data files, 3 rd bit – output supercell cif file, 4 th
	bit – output Gaussian oniom input files. The bit-wise output
	control setting can be combined.
temp	Default to 300
maxt	Default to 10000
ratetype	Default to marcus, can be marcus, quantum.

sta	Default to 1, if use short-time approximation.
nsimu	Default to 2000
tsimu	Default to 1000 ns
tsnap	Default to 5 ns
iterlimit	Default to 100
nevery_out	Default to 10
HL_unique_mol	Default to 1, can be 0 or 1
RE_unique_mol	Default to 1, can be 0 or 1
molecule	Default to "2 mol1.mol mol2.mol" with -mol option
crystal	Default to "naphthalene.cif"
bond_dis_scale	Default to 1.15, used to help separating molecules in cif file,
	users may tune this parameter for abnormal cases.
HL_unique_ctrl_ratio	Default to 0.05, used for judging unique dipoles.
	eigval[i] - eigval[j] / max(eigval[i] , eigval[j]) < 0.05
RE_use_neutral_chk	Calculate anion and cation state reorganization energies by
	using neutral state chk file, can be 0 or 1, default to 0.
RE_calc_lambda_4P	If calculate reorganization energies by using the Nelson four-
	point method, can be 0 or 1, default to 1.
Thinfilm	Format: thinfilm = dir nuc, here dir can be
	<pre>0(vector_a),1(vector_b), and 2(vector_c),</pre>
	nuc is the number of repeating unit cell in dir direction,
	e.g., thinfilm = 0 2
V_dynamic_disorder	Default to 0, used to control if we need to calculate dynamic
	disorder of transfer integrals, the per-molecular files $\ensuremath{\mathbb{VH}}\xspace +$ –
	dyn.dat or VL*-dyn.dat are to be provided under
	data directory.
HOMOLUMO_dynamic_disorder	Default to 0, used to control if we need to calculate dynamic
	disorder of HOMO/LUMO, files HOMO-dyn.dat or
	LUMO-dyn.dat are to be provided under data directory.

12. PYSOC input variables

do_pysoc	Default to 0, can be 0 or 1, for PYSOC calculations
sched_type	Scheduling type, can be pbs, slurm, lsf, or local.
queue_name	Scheduling queue name
qc_exe	Default to g09, can be g09 or g16
qc_memory	Default to 4096, in MB
qc_nodes	Default to 1
qc_ppn	Default to 1
module_qc	Use module to setup QC running environment
pysoc_QM_code	Can be gauss_tddft or tddftb
pysoc_QM_input_file	Used only by gauss_tddft
n_excited_singlets	Default to 0, can be set to, say, 4
n_excited_triplets	Default to 0, can be set to, say, 4
soc_scale	Default to 1.0
cicoeff_thresh	Default to 1.0e-5
bIncludeGroundState	Default to 'True', can be 'True' or 'False'

Note: Use equal sign (=) to assign variables, e.g., temp = 300.

13. MOMAP Tools

13.1 MOMAP tool for preparing Gaussian oniom input files

The process to prepare for the Gaussian oniom input files is very tedious and error-prone, here we've written a program called momap_preponiom.exe to do the job. For example, we can use the --help or -h option to see the various available options, e.g.:

```
[qkli@localhost oniom-input]$ momap geninp.exe --help
                                                                   *****
* MOMAP Calculation Utility, Version 2022A (2.3.3) build on Apr 24 2022
  Zhigang Shuai Group, Department of Chemistry, Tsinghua University, Beijing *
****
                           ***********
Momap Input (momap.inp) Generation Utility
Usage: momap_geninp.exe [opts]
 -config s : set config file, default to momap.inp
  -cif
                  : use cif file as molecule input (default)
 -mol
                 : use mol file as molecule input
 -moi : use moi life as molecule input
-module : set to use environment module flag
-terse : generate terse momap.inp (default)
-verbose : generate verbose momap.inp
-oldconfig : generate old config.inp
                 : generate old config.inp
 -orca : use ORCA compute engine
-qchem : use Q-Chem compute engine
-oniom : generate oniom input files
e.g.: momap_geninp.exe
 momap geninp.exe -config momap.inp
 momap_geninp.exe -verbose
 momap geninp.exe -cif
 momap geninp.exe -mol
 momap_geninp.exe -module
 momap geninp.exe -config momap.inp -verbose
 momap_geninp.exe -oldconfig
 momap geninp.exe -orca
 momap geninp.exe -oniom
```

Before we can use the program, we need the momap.inp file which can be generated by using the MOMAP tool momap geninp.exe, and its usage is as follows:

The normal process to prepare the Gaussian oniom input files is as follows:

 Generate momap.inp for momap_preponiom.exe by using momap_geninp.exe with the option -oniom:

```
[qkli@localhost oniom-input]$ momap_geninp.exe -oniom
*** Momap Input Generation Utility...
Writing config file "momap.inp"...
Writting run script file 'run.sh'...
*** Successfully done.
[qkli@localhost oniom-input]$
```

The contents of the generated momap.inp is as follows:

```
&transport
 do transport prepare = 1
 qc method
                      = b3lyp
 qc_basis
                      = b3lyp 6-31g*
                      = b3lyp 6-31g*
 qc basis re
                       = 8192 ! MB
 qc memory
 qc_ppn
                       = 8
                      = 4 ! for neighbor list construction
 lat cutoff
 oniom_output_flag = 1
oniom_nlayers = 2
oniom_com_cutoff = 50
                                   ! if set to 1 to output oniom input files
                                    ! maximum 3 layers, default to 2
                                   ! molecular COM cutoff in angstroms
 crystal
                      = naphthalene.cif
```

Now we can modify the momap . inp according to our specific requirements. The most important parameter is the oniom_nlayers, it can be 1, 2 or 3, and it defaults to 2, that is, including up to the 2nd nearest neighbors for the each central molecule in the unit cell. At the moment, the utility can only generate the oniom model at most up to the 3rd layer. Another parameter we need to pay attention to is the oniom_com_cutoff, by using the parameter properly we can significantly reduce the number of atoms in the oniom model for the elongated molecules without affecting the oniom calculation results too much.

2) Generate the oniom files by running momap_preponiom.exe as follows:

```
[qkli@localhost oniom-input]$ momap preponiom.exe
***** Perform MOMAP Oniom Input Preparation...
Reading config file "momap.inp"...
Reading crystal file "naphthalene.cif"...
 Identifier: naphthalene
 Spacegroup name: 'P1'
 Spacegroup operations:
   x,y,z
 Cell lattice a = 8.098
 Cell lattice b = 5.953
 Cell lattice c = 8.652
 Cell lattice alpha = 90
 Cell lattice beta = 124.4
 Cell lattice gamma = 90
 natoms cif = 36
 First atom: C1 C 0.082321 0.018562 0.328357
 . . .
 Last atom: H36 H 0.466698 0.795196 0.331298
 Unit cell nmols = 2
 Unit cell natoms = 18 18
Crystal file naphthalene.cif parsing done.
Make whole molecules...
 molecule 1 \text{ COM} = -0.000000 0.000000 0.0000000
 molecule 2 \text{ COM} = 0.500000 0.500000 - 0.000000
**** MOMAP Build Neighbor List ****
 Neighbor rcutoff distance: 4
 Neighbor search cell (-/+): 3 3 3
**** End of MOMAP Build Neighbor List ****
**** Check Duplicate 2mol pairs ****
 Unique 2mol pairs: 5 out of 28
    1 1 <=>
                1
     1 5 <=>
                  5
     1 7 <=>
                 7
          <=> 11
     1 11
     1 13
                13
           <=>
**** End of Check Duplicate 2mol pairs ****
**** Check RE Duplicate Molecules in Unit Cell ****
 Unit cell molecular indexes: 1 1
 Unit cell unique molecular indexes: 1
**** End of Check RE Duplicate Molecules in Unit Cell ****
**** Check HL Duplicate Molecules in Unit Cell ****
 Unit cell molecular indexes: 1 1
 Unit cell unique molecular indexes: 1
**** End of Check HL Duplicate Molecules in Unit Cell ****
**** Generate Oniom input files ****
 data/mol1 oniom.com
 data/moll oniom.xyz
 data/mol2 oniom.com
 data/mol2 oniom.xyz
**** End of Generate Oniom input files ****
***** MOMAP Oniom Input Preparation Successfully Done.
[qkli@localhost oniom-input]$
```

The files generated are shown as follows:



Here the moll_oniom.com and mol2_oniom.com are the needed Gaussian input files which can also be visualized by using the GaussView as follows:

